



## PDSMAN – EZYEDIT SPACE

*Bruce Koss*

*Wells Fargo*

*Monday, August 10, 2015*

*3:15 PM - 4:15 PM*

*17410*

[www.SHARE.org](http://www.SHARE.org)



#SHAREorg



**SHARE is an independent volunteer-run information technology association  
that provides education, professional networking and industry influence.**



# EZYEDIT – SPACE

- The **SPACE** command displays DASD volume information, including the following:
  - Amount of free space available
  - Volume and VTOC utilization statistics
  - Extended Address Volume (EAV) information
- Can be executed in batch (**PDSEASY**)
- The next few slides provide an overview and demonstrate how to use the **SPACE** command

# Agenda

Topic	Description
<a href="#"><u>Invocation</u></a>	How to invoke the <b>SPACE</b> command within EZYEDIT
<a href="#"><u>Views</u></a>	Overview of the panels displayed
<a href="#"><u>Commands</u></a>	Primary and line commands
<a href="#"><u>Batch</u></a>	How to code and execute <b>SPACE</b> in a batch job
<a href="#"><u>Links</u></a>	PDSMAN and other slide decks
<a href="#"><u>Conclusion</u></a>	Final comments


# Attachments (0)

- The following attachments are included in this document:

File	Type
EZYEDIT – Commands – Pages 2	PDF
EZYEDIT – Commands – Pages 3	PDF
EZYEDIT – Commands – Pages 6	PDF
Page 35 – SPACE – Volume	TXT
Page 37 – SPACE – Address	TXT
Page 39 – SPACE – Storage Group	TXT
Page 41 – SPACE – Volume Summary	TXT
Page 43 – SPACE – Volume Space	TXT
Page 45 – SPACE – USAGE	TXT

# Attachments (0)

- Invoke Adobe Reader and click the ‘Attachments’ button on the left side of the navigational panel of the main Reader window



# Disclaimers

- Must use Adobe Reader to view attachments
  - (📎) signifies attachment
- May need to adjust the Adobe Reader zoom value to view text
- Commands and screens may be slightly different depending on the operating system's version and release level
  - These commands and screen prints were executed on
    - **PDSMAN/EZYEDIT V7.70** and **z/OS V2R1**
- Security may prevent access to panels or executing commands
- For more detailed information, please reference the following manual:
  - **CA PDSMAN PDS Library Management**
    - **EZYEDIT User Guide**
      - **Chapter 8, Volume Information Display**

# Invocation

# Overview

---

- The next few slides demonstrate how to invoke the **SPACE** command from within EZYEDIT
- Wild cards are accepted
  - +, ? and % represent a single character
  - \* represents a string

# SPACE

- From the Ezyedit Selection Panel, type in **SPACE** in the **Function** field and press **ENTER**

```
----- PDSMAN 7.70 - Ezyedit Selection Panel -----
COMMAND ==>                               SCROLL ==> CSR

Function      ==> SPACE          06:10          Project ==>
DSN/Variable # ==>                      Group ==>
Member Name    ==>                      Type ==>
Volume Serial  ==>          Printer ==>       Profile ==>

1 DSN= /*----- DATASETS -----*/           2 DSN= /*----- TSO COMMANDS -----*/
3 DSN= 'TSTSS.R2221.JCL.*'                   4 DSN= TSO LISTC
5 DSN= 'TSTSS.R2221.JCL.CNTL(JCL*)'         6 DSN= TSO SYSID
7 DSN= 'TSTSS.R2221.JCL.CNTL(TST%0*)'        8 DSN= TSO WHOAMI
9 DSN=                                         10 DSN=
11 DSN= /*----- PERSONAL LISTS -----*/        12 DSN= /*---- EZYEDIT COMMANDS ---*/
13 DSN= @MYISPF                                14 DSN= APFLIST
15 DSN= @MYDSNS                                16 DSN= LLALIST
17 DSN=                                         18 DSN= LNKLIST
19 DSN= /*--- ALLOCATION DISPLAY ---*/        20 DSN= LPALIST
21 DSN= F(*)                                    22 DSN= PDSMINIT
23 DSN= F(ISP*)                                24 DSN=
25 DSN= F(SYSPROC)                            26 DSN=

Press F1 Key for Tutorial and Command Summary
```

# SPACE – Results

- Results from executing the command

EZYEDIT Volume Information *							Row 1 of 3507			
							SCROLL ==> CSR			
<----- Volume Freespace ----->							<--- Largest --->			
Volume	Cua	Cyls--Trks--Byts	Freespace	Free%	...25...	50...	75...	100	Cap	Cyls--Trks--Byts
AKT030	1EDB	42024	630K 35.7G	64%					55.7G	42016 630K 35.7G
AKT100	10DF	39015	585K 33.2G	15%					223G	3599 53985 3.06G
AKT300	1F1B	28341	427K 24.2G	43%					55.7G	25844 388K 22G
AKT301	11DA	65094	976K 55.3G	99%					55.7G	65094 976K 55.3G
AKT601	109F	23312	350K 19.8G	9%					223G	9090 136K 7.73G
AKT602	11DF	49779	747K 42.3G	19%					223G	26329 395K 22.4G
CPLT00	2B02	3063	45961 2.6G	92%					2.84G	3063 45947 2.6G
CPLT01	2B0A	3170	47578 2.7G	95%					2.84G	3170 47564 2.7G
CPLT02	2B12	3254	48829 2.77G	97%					2.84G	3254 48815 2.77G
CPLT03	2B1A	3254	48828 2.77G	97%					2.84G	3254 48820 2.77G
CPLT04	2B22	3254	48828 2.77G	97%					2.84G	3254 48820 2.77G
CPLT05	2B2A	3254	48829 2.77G	97%					2.84G	3254 48815 2.77G
CPLT06	2B32	3170	47578 2.7G	95%					2.84G	3170 47564 2.7G
CPLT07	2B3A	3063	45961 2.6G	92%					2.84G	3063 45947 2.6G
CPLT10	2D0A	3063	45961 2.6G	92%					2.84G	3063 45947 2.6G
CPLT11	2D12	3170	47578 2.7G	95%					2.84G	3170 47564 2.7G
CPLT12	2D1A	3254	48829 2.77G	97%					2.84G	3254 48815 2.77G
CPLT13	2D22	3254	48828 2.77G	97%					2.84G	3254 48820 2.77G

# SPACE – Volume

- Type in **SPACE** in the **Function** field, type in the DASD volume in the **Volume Serial** field and press **ENTER**

```
----- PDSMAN 7.70 - Ezyedit Selection Panel -----
COMMAND ===>                               SCROLL ===> CSR

Function      ===> SPACE          06:11           Project ===>
DSN/Variable # ===>                      Group    ===>
Member Name   ===>                      Type     ===>
Volume Serial ===> AKT*           Printer ===>       Profile ===>

1 DSN= /*----- DATASETS -----*/      2 DSN= /*----- TSO COMMANDS -----*/
3 DSN= 'TSTSS.R2221.JCL.*'            4 DSN= TSO LISTC
5 DSN= 'TSTSS.R2221.JCL.CNTL(JCL*)'  6 DSN= TSO SYSID
7 DSN= 'TSTSS.R2221.JCL.CNTL(TST%0*)' 8 DSN= TSO WHOAMI
9 DSN=                                     10 DSN=
11 DSN= /*----- PERSONAL LISTS -----*/ 12 DSN= /*---- EZYEDIT COMMANDS ---*/
13 DSN= @MYISPF                         14 DSN= APFLIST
15 DSN= @MYDSNS                         16 DSN= LLALIST
17 DSN=                                     18 DSN= LNKLIST
19 DSN= /*--- ALLOCATION DISPLAY ---*/  20 DSN= LPALIST
21 DSN= F(*)                            22 DSN= PDSMINIT
23 DSN= F(ISP*)                         24 DSN=
25 DSN= F(SYSPROC)                      26 DSN=

Press F1 Key for Tutorial and Command Summary
```

# SPACE – Volume – Results

- Results from executing the command

EZYEDIT Volume Information * ----- Row 1 of 3507								
				SCROLL ==> CSR				
Volume	<----- Volume Freespace ----->				<--- Largest --->			
	Cua	Cyls--Trks--Byts	Free%	...25...50...75..100	Cap	Cyls--Trks--Byts		
AKT030	1EDB 42024	630K 35.7G	64%	F	55.7G 42016	630K 35.7G		
AKT100	10DF 39015	585K 33.2G	15%	F	223G 3599	53985 3.06G		
AKT300	1F1B 28341	427K 24.2G	43%	F	55.7G 25844	388K 22G		
AKT301	11DA 65094	976K 55.3G	99%	F	55.7G 65094	976K 55.3G		
AKT601	109F 23312	350K 19.8G	9%	F	223G 9090	136K 7.73G		
AKT602	11DF 49779	747K 42.3G	19%	F	223G 26329	395K 22.4G		

# SPACE – Unit

- Type in **SPACE** in the **Function** field, type in forward slash (/) and the DASD control unit address in the **Volume Serial** field and press **ENTER**

```
----- PDSMAN 7.70 - Ezyedit Selection Panel -----
COMMAND ==>                               SCROLL ==> CSR

Function      ==> SPACE          06:12           Project ==>
DSN/Variable # ==>                      Group ==>
Member Name    ==>                      Type ==>
Volume Serial  ==> /109*          Printer ==>       Profile ==>

1 DSN= /*----- DATASETS -----*/      2 DSN= /*----- TSO COMMANDS -----*/
3 DSN= 'TSTSS.R2221.JCL.*'              4 DSN= TSO LISTC
5 DSN= 'TSTSS.R2221.JCL.CNTL(JCL*)'   6 DSN= TSO SYSID
7 DSN= 'TSTSS.R2221.JCL.CNTL(TST%0*)' 8 DSN= TSO WHOAMI
9 DSN=                                     10 DSN=
11 DSN= /*----- PERSONAL LISTS -----*/ 12 DSN= /*---- EZYEDIT COMMANDS ---*/
13 DSN= @MYISPF                           14 DSN= APFLIST
15 DSN= @MYDSNS                           16 DSN= LLALIST
17 DSN=                                     18 DSN= LNKLIST
19 DSN= /*--- ALLOCATION DISPLAY ---*/   20 DSN= LPALIST
21 DSN= F(*)                             22 DSN= PDSMINIT
23 DSN= F(ISP*)                          24 DSN=
25 DSN= F(SYSPROC)                      26 DSN=

Press F1 Key for Tutorial and Command Summary
```

# SPACE – Unit – Results

- Results from executing the command

EZYEDIT Volume Information Unit=109* ----- Row 1 of 16						
COMMAND ==> SCROLL ==> CSR						
Volume	Cua	Volume Freespace			<--- Largest --->	
		Cyls--Trks--Byts	Free%	...25...50...75..100	Cap	Cyls--Trks--Byts
AKT601	109F	23312	350K	19.8G	9%	223G
DBC022	109A	17846	268K	15.2G	27%	55.7G
DIMS15	109C	11000	166K	9.42G	17%	55.7G
DMD113	109E	20586	309K	17.5G	31%	55.7G
DMD118	109B	23506	356K	20.2G	36%	55.7G
DMD178	1092	29873	449K	25.5G	46%	55.7G
DMD218	1093	27260	410K	23.2G	42%	55.7G
DXL137	1096	28667	430K	24.4G	44%	55.7G
DXL262	1097	7336	110K	6.24G	11%	55.7G
DXSB71	1095	17624	265K	15G	27%	55.7G
DXSB73	1094	22867	344K	19.5G	35%	55.7G
ZA109D	109D	65517	983K	55.7G	100%	55.7G
ZA1090	1090	65517	983K	55.7G	100%	55.7G
ZA1091	1091	65517	983K	55.7G	100%	55.7G
ZA1098	1098	65517	983K	55.7G	100%	55.7G
ZA1099	1099	65517	983K	55.7G	100%	55.7G
***** Bottom of Data *****						

# SPACE – Storage Group

- Type in **SPACE** in the **Function** field, type in **SG=[storagegroup]** in the **DSN/Variable #** field and press **ENTER**

```
----- PDSMAN 7.70 - Ezyedit Selection Panel -----
COMMAND ===>                               SCROLL ===> CSR

Function      ===> SPACE          06:13           Project ===>
DSN/Variable # ===> SG=AKTPOL        Member Name ===>           Group ===>
                                         Volume Serial ===>           Type ===>
                                         Printer ===>           Profile ===>

1 DSN= /*----- DATASETS -----*/      2 DSN= /*----- TSO COMMANDS -----*/
3 DSN= 'TSTSS.R2221.JCL.*'            4 DSN= TSO LISTC
5 DSN= 'TSTSS.R2221.JCL.CNTL(JCL*)'  6 DSN= TSO SYSID
7 DSN= 'TSTSS.R2221.JCL.CNTL(TST%0*)' 8 DSN= TSO WHOAMI
9 DSN=                                     10 DSN=
11 DSN= /*----- PERSONAL LISTS -----*/ 12 DSN= /*---- EZYEDIT COMMANDS ---*/
13 DSN= @MYISPF                         14 DSN= APFLIST
15 DSN= @MYDSNS                         16 DSN= LLALIST
17 DSN=                                     18 DSN= LNKLIST
19 DSN= /*--- ALLOCATION DISPLAY ---*/  20 DSN= LPALIST
21 DSN= F(*)                            22 DSN= PDSMINIT
23 DSN= F(ISP*)                         24 DSN=
25 DSN= F(SYSPROC)                      26 DSN=

Press F1 Key for Tutorial and Command Summary
```

# SPACE – Storage Group – Results

- Results from executing the command

EZYEDIT Volume Information * ----- Row 1 of 3507							
COMMAND ===> SCROLL ===> CSR							
<----- Volume Freespace ----->				<--- Largest --->			
Volume Cua Cyls--Trks--Byts Free% ...25...50...75..100				Cap Cyls--Trks--Byts			
-----	-----	-----	-----	-----	-----	-----	-----
AKT030 1EDB 42024 630K 35.7G 64%					55.7G 42016 630K 35.7G		
AKT100 10DF 39015 585K 33.2G 15%					223G 3599 53985 3.06G		
AKT601 109F 23312 350K 19.8G 9%					223G 9090 136K 7.73G		
AKT602 11DF 49779 747K 42.3G 19%					223G 26329 395K 22.4G		

# Views

# Overview

- The next few slides display the following volume information views:

Panel	Description
Freespace	Displays volume free space information including the largest contiguous space available on the volume
Usage	Displays volume, VTOC and VTOC Index usage information
Summary	Displays the fragmentation index, device type and volume status information
Space	Displays the total volume space, the total volume free space and the size of the largest contiguous free space in cylinders, tracks and bytes
Track Managed	Displays the total space, free space and the size of the largest contiguous free space in the track managed area of the volume <ul style="list-style-type: none"> <li>This screen is displayed <u>only</u> when showing information for Extended Address Volumes (EAVs)</li> </ul>

# SPACE – Volume

- Type in **SPACE** in the **Function** field, type in the DASD volume in the **Volume Serial** field and press **ENTER**

```
----- PDSMAN 7.70 - Ezyedit Selection Panel -----
COMMAND ===>                               SCROLL ===> CSR

Function      ===> SPACE          06:13           Project ===>
DSN/Variable # ===>                      Group    ===>
Member Name   ===>                      Type     ===>
Volume Serial ===> DPS*           Printer ===> Profile   ===>

1 DSN= /*----- DATASETS -----*/      2 DSN= /*----- TSO COMMANDS -----*/
3 DSN= 'TSTSS.R2221.JCL.*'            4 DSN= TSO LISTC
5 DSN= 'TSTSS.R2221.JCL.CNTL(JCL*)'  6 DSN= TSO SYSID
7 DSN= 'TSTSS.R2221.JCL.CNTL(TST%0*)' 8 DSN= TSO WHOAMI
9 DSN=                                     10 DSN=
11 DSN= /*----- PERSONAL LISTS -----*/ 12 DSN= /*---- EZYEDIT COMMANDS ---*/
13 DSN= @MYISPF                         14 DSN= APFLIST
15 DSN= @MYDSNS                         16 DSN= LLALIST
17 DSN=                                     18 DSN= LNKLIST
19 DSN= /*--- ALLOCATION DISPLAY ---*/  20 DSN= LPALIST
21 DSN= F(*)                            22 DSN= PDSMINIT
23 DSN= F(ISP*)                         24 DSN=
25 DSN= F(SYSPROC)                      26 DSN=

Press F1 Key for Tutorial and Command Summary
```

# SPACE – Freespace View

- Displays the **Volume** and **Largest Freespace** information; press **F11** (RIGHT) to display the **Usage** information

EZYEDIT Volume Information Vol=DPS*							Row 1 of 17			
							SCROLL ==> CSR			
Volume	Cua	Volume Freespace					<--- Largest --->			
		Cyls--Trks--Byts	Free%	...25...	50...	75..100	Cap	Cyls--Trks--Byts		
DPS001	18DC	24286	364K	20.7G	37%		55.7G	17585	264K	15G
DPS002	18A3	18741	281K	15.9G	29%		55.7G	15373	231K	13.1G
DPS003	185C	18214	273K	15.5G	28%		55.7G	17375	261K	14.8G
DPS004	181C	28492	427K	24.2G	43%		55.7G	25069	376K	21.3G
DPS005	17DC	33767	507K	28.7G	52%		55.7G	32239	484K	27.4G
DPS006	17A1	38743	581K	32.9G	59%		55.7G	37198	558K	31.6G
DPS007	175C	25340	380K	21.6G	39%		55.7G	24960	374K	21.2G
DPS031	171C	6120	91890	5.21G	9%		55.7G	4112	61680	3.5G
DPS032	245B	16882	253K	14.4G	26%		55.7G	6867	103K	5.84G
DPS033	241B	7330	110K	6.25G	11%		55.7G	2597	38955	2.21G
DPS034	23DB	5228	78633	4.46G	8%		55.7G	2736	41043	2.33G
DPS035	239D	5289	79459	4.5G	8%		55.7G	2910	43650	2.47G
DPS036	235B	5275	79290	4.49G	8%		55.7G	1636	24540	1.39G
DPS037	231B	5816	87442	4.95G	9%		55.7G	2850	42755	2.42G
DPS038	22DB	10867	163K	9.24G	17%		55.7G	4788	71828	4.07G
DPS039	225B	5240	78727	4.46G	8%		55.7G	2148	32221	1.83G
DPS040	229D	164	2610	148M	0%		55.7G	76	1154	65.4M
***** Bottom of Data *****										

# SPACE – Usage View

- Displays the **Volume** and **Vtoc Usage** information; press **F11 (RIGHT)** to display the **Summary** information

EZYEDIT Volume Information Vol=DPS*							Row 1 of 17			
							SCROLL ==> CSR			
Volume	Cua	<----- Volume Usage ----->				<----- Vtoc Usage ----->				
		Tracks	Free	Used%	...25...50...75..100	Vtoc#	Vtoc%	Ind	Ind#	Ind%
DPS001	18DC	983K	364K	63%		900	2%	Act	300	2%
DPS002	18A3	983K	281K	71%		900	2%	Act	300	2%
DPS003	185C	983K	273K	72%		900	2%	Act	300	2%
DPS004	181C	983K	427K	57%		900	2%	Act	300	2%
DPS005	17DC	983K	507K	48%		900	2%	Act	300	2%
DPS006	17A1	983K	581K	41%		900	2%	Act	300	2%
DPS007	175C	983K	380K	61%		900	2%	Act	300	2%
DPS031	171C	983K	91890	91%		>1K	2%	Act	900	1%
DPS032	245B	983K	253K	74%		900	3%	Act	600	1%
DPS033	241B	983K	110K	89%		900	5%	Act	600	1%
DPS034	23DB	983K	78633	92%		900	3%	Act	600	1%
DPS035	239D	983K	79459	92%		900	3%	Act	600	1%
DPS036	235B	983K	79290	92%		900	4%	Act	600	1%
DPS037	231B	983K	87442	91%		>1K	2%	Act	900	1%
DPS038	22DB	983K	163K	83%		>1K	2%	Act	900	1%
DPS039	225B	983K	78727	92%		900	3%	Act	300	2%
DPS040	229D	983K	2610	100%		900	3%	Act	300	2%
***** Bottom of Data *****										

# SPACE – Summary View

- Displays the **Volume Summary** information; press F11 (RIGHT) to display the **Space** information

EZYEDIT Volume Information Vol=DPS* ----- Row 1 of 17 COMMAND ===>									
<----- Volume Summary ----->									
Volume	Cua	Trk/Cyl	Tracks	Free	Frag	Device	Access	Mount	Status
DPS001	18DC	15	983K	364K	63	3390-9	DPSPOL	Private	Enabled
DPS002	18A3	15	983K	281K	42	3390-9	DPSPOL	Private	Enabled
DPS003	185C	15	983K	273K	20	3390-9	DPSPOL	Private	Enabled
DPS004	181C	15	983K	427K	36	3390-9	DPSPOL	Private	Enabled
DPS005	17DC	15	983K	507K	16	3390-9	DPSPOL	Private	Enabled
DPS006	17A1	15	983K	581K	17	3390-9	DPSPOL	Private	Enabled
DPS007	175C	15	983K	380K	7	3390-9	DPSPOL	Private	Enabled
DPS031	171C	15	983K	91890	93	3390-9	DPSPOL	Private	Enabled
DPS032	245B	15	983K	253K	110	3390-9	DPSPOL	Private	Enabled
DPS033	241B	15	983K	110K	139	3390-9	DPSPOL	Private	Enabled
DPS034	23DB	15	983K	78633	136	3390-9	DPSPOL	Private	Enabled
DPS035	239D	15	983K	79459	126	3390-9	DPSPOL	Private	Enabled
DPS036	235B	15	983K	79290	174	3390-9	DPSPOL	Private	Enabled
DPS037	231B	15	983K	87442	131	3390-9	DPSPOL	Private	Enabled
DPS038	22DB	15	983K	163K	121	3390-9	DPSPOL	Private	Enabled
DPS039	225B	15	983K	78727	145	3390-9	DPSPOL	Private	Enabled
DPS040	229D	15	983K	2610	258	3390-9	DPSPOL	Private	Enabled
***** Bottom of Data *****									

# SPACE – Space View

- Displays the **Volume Space** information; press **F11 (RIGHT)** to re-display the **Freespace** information

EZYEDIT Volume Information Vol=DPS* ----- Row 1 of 17									
COMMAND ===> SCROLL ==> CSR									
Volume	Cua	Volume Space <----- ----->							
		T-Cyl	T-Trk	T-Byt	F-Cyl	F-Trk	F-Byt	F-Ext	L-Cyl
DPS001	18DC	65520	983K	55.7G	24286	364K	20.7G	20	17585
DPS002	18A3	65520	983K	55.7G	18741	281K	15.9G	24	15373
DPS003	185C	65520	983K	55.7G	18214	273K	15.5G	22	17375
DPS004	181C	65520	983K	55.7G	28492	427K	24.2G	29	25069
DPS005	17DC	65520	983K	55.7G	33767	507K	28.7G	23	32239
DPS006	17A1	65520	983K	55.7G	38743	581K	32.9G	15	37198
DPS007	175C	65520	983K	55.7G	25340	380K	21.6G	27	24960
DPS031	171C	65520	983K	55.7G	6120	91890	5.21G	25	4112
DPS032	245B	65520	983K	55.7G	16882	253K	14.4G	35	6867
DPS033	241B	65520	983K	55.7G	7330	110K	6.25G	58	2597
DPS034	23DB	65520	983K	55.7G	5228	78633	4.46G	54	2736
DPS035	239D	65520	983K	55.7G	5289	79459	4.5G	31	2910
DPS036	235B	65520	983K	55.7G	5275	79290	4.49G	36	1636
DPS037	231B	65520	983K	55.7G	5816	87442	4.95G	29	2850
DPS038	22DB	65520	983K	55.7G	10867	163K	9.24G	18	4788
DPS039	225B	65520	983K	55.7G	5240	78727	4.46G	34	2148
DPS040	229D	65520	983K	55.7G	164	2610	148M	31	76
***** Bottom of Data *****									

# Commands

# Overview

- The next few slides display all the EZYEDIT DASD **SPACE** primary and line commands
- The **Batch** column displays
  - **Yes**, can be used with PDSEASY
  - **No**, can not be used with PDSEASY

# SPACE – Primary Commands (@)

Command	Batch	Description
<u>Find</u>	Yes	Find a string
<u>HardCopy</u>	Yes	Print current list
<u>IF</u>	Yes	Conditional filter
<u>Include</u>	Yes	Include additional volumes
<u>LEFT</u>	Yes	Scroll left
<u>Locate</u>	Yes	Locate a volume
<u>ONLY</u>	Yes	Exclude rows not containing argument
<u>OUTput</u>	Yes	Output current list
<u>POPlist</u>	Yes	Restore list from the display stack
<u>PUSHlist</u>	Yes	Save list to the display stack
<u>REFresh</u>	Yes	Rebuild display
<u>RESET</u>	Yes	Reset display
<u>RIGHT</u>	Yes	Scroll right

# SPACE – Primary Commands (@)

Command	Batch	Description
S	No	Dataset list
SORT	Yes	SORT display
USAGE	Yes	Volume usage summary
X	Yes	Exclude above or below

# SPACE – Primary Command – USAGE

- To display the **Volume Usage Summary** report, type in **USAGE** and press **ENTER**

EZYEDIT Volume Information Vol=DPS*							Row 1 of 17			
COMMAND ===> <b>USAGE</b>							SCROLL ===> CSR			
Volume	Volume Freespace				<--- Largest --->					
	Volume	Cua	Cyls--Trks--Byts	Free%	...25...	50...	75...	100	Cap	Cyls--Trks--Byts
DPS001	18DC	24286	364K 20.7G	37%					55.7G	17585 264K 15G
DPS002	18A3	18741	281K 15.9G	29%					55.7G	15373 231K 13.1G
DPS003	185C	18214	273K 15.5G	28%					55.7G	17375 261K 14.8G
DPS004	181C	28492	427K 24.2G	43%					55.7G	25069 376K 21.3G
DPS005	17DC	33767	507K 28.7G	52%					55.7G	32239 484K 27.4G
DPS006	17A1	38743	581K 32.9G	59%					55.7G	37198 558K 31.6G
DPS007	175C	25340	380K 21.6G	39%					55.7G	24960 374K 21.2G
DPS031	171C	6120	91890 5.21G	9%					55.7G	4112 61680 3.5G
DPS032	245B	16882	253K 14.4G	26%					55.7G	6867 103K 5.84G
DPS033	241B	7330	110K 6.25G	11%					55.7G	2597 38955 2.21G
DPS034	23DB	5228	78633 4.46G	8%					55.7G	2736 41043 2.33G
DPS035	239D	5289	79459 4.5G	8%					55.7G	2910 43650 2.47G
DPS036	235B	5275	79290 4.49G	8%					55.7G	1636 24540 1.39G
DPS037	231B	5816	87442 4.95G	9%					55.7G	2850 42755 2.42G
DPS038	22DB	10867	163K 9.24G	17%					55.7G	4788 71828 4.07G
DPS039	225B	5240	78727 4.46G	8%					55.7G	2148 32221 1.83G
DPS040	229D	164	2610 148M	0%					55.7G	76 1154 65.4M
***** Bottom of Data *****										

# SPACE – USAGE – Results

- Displays the Storage Usage Summary report

```
EZYEDIT Utility Report ----- Row 1 of 7
COMMAND ===> SCROLL ===> CSR

Storage Usage Summary

Total Tracks= 16,711,000 Free= 3,840,104 Usage= 77%

Volume(s) processed : 17
***** Bottom of Data *****
```

# SPACE – Line Commands (l)

Command	Batch	Description
S	No	Displays a dataset list on the volume
U	No	User command alias
X	No	Exclude a volume
=	No	Repeat command
/	No	Scroll display
?	No	Re-display message

# SPACE – Line Command – S

- To display all the datasets on the DASD volume, tab down to a DASD volume, type in **S** and press **ENTER**

EZYEDIT Volume Information Vol=DPS*							Row 1 of 17			
COMMAND ===>							SCROLL ===> CSR			
<----- Volume Freespace -----> <--- Largest --->										
Volume	Cua	Cyls--Trks--Byts	Free%	...25...	50...	75..100	Cap	Cyls--Trks--Byts		
S001	18DC	24286	364K	20.7G	37%		55.7G	17585	264K	15G
DPS002	18A3	18741	281K	15.9G	29%		55.7G	15373	231K	13.1G
DPS003	185C	18214	273K	15.5G	28%		55.7G	17375	261K	14.8G
DPS004	181C	28492	427K	24.2G	43%		55.7G	25069	376K	21.3G
DPS005	17DC	33767	507K	28.7G	52%		55.7G	32239	484K	27.4G
DPS006	17A1	38743	581K	32.9G	59%		55.7G	37198	558K	31.6G
DPS007	175C	25340	380K	21.6G	39%		55.7G	24960	374K	21.2G
DPS031	171C	6120	91890	5.21G	9%		55.7G	4112	61680	3.5G
DPS032	245B	16882	253K	14.4G	26%		55.7G	6867	103K	5.84G
DPS033	241B	7330	110K	6.25G	11%		55.7G	2597	38955	2.21G
DPS034	23DB	5228	78633	4.46G	8%		55.7G	2736	41043	2.33G
DPS035	239D	5289	79459	4.5G	8%		55.7G	2910	43650	2.47G
DPS036	235B	5275	79290	4.49G	8%		55.7G	1636	24540	1.39G
DPS037	231B	5816	87442	4.95G	9%		55.7G	2850	42755	2.42G
DPS038	22DB	10867	163K	9.24G	17%		55.7G	4788	71828	4.07G
DPS039	225B	5240	78727	4.46G	8%		55.7G	2148	32221	1.83G
DPS040	229D	164	2610	148M	0%		55.7G	76	1154	65.4M
***** Bottom of Data *****										

# SPACE – S – Results

- Displays all datasets on the DASD volume

```

EZYEDIT Dataset List * Vol=DPS001 ----- Row 1 of 1052
COMMAND ===> SCROLL ==> CSR
Enter: S=Select D=Delete F=Space-Rel R=Rename I=Vtoc-Info Z=Compress F1=Help
Command   Name                               Message      Volume
----- 
DVPDM1.DATACOM.CAILIB                      DPS001
DVPES1.OPSMVS.SET1.LOADLIB                  DPS001
DVPSS1.TSS.CAILOADA.DV27                   DPS001
DVPSS1.TSS.CAILOADDB.DV27.D15015            DPS001
PRDDM.#DMS.PINSTALL.SET1                   DPS001
PRDH.C.#CNMXX.P3.ZMAILMON.BKUP              DPS001
PRDH.C.#NET.EA.REPORT.JCL                  DPS001
PRDH.C.#NET.FTPCHK2#.FCEE18SO               DPS001
PRDH.C.#NET.FTPCHK22.FCDV23SO               DPS001
PRDH.C.#NET.FTPCHK22.FCEE09SO               DPS001
PRDH.C.#NET.FTPSMF.DAILY.EMAIL.D13169       DPS001
PRDH.C.#NET.FTPSMF.DAILY.EMAIL.D13172       DPS001
PRDH.C.#NET.FTPSMF.DAILY.EMAIL.D13193       DPS001
PRDH.C.#NET.FTPSMF.DAILY.EMAIL.D13195       DPS001
PRDH.C.#NET.FTPSMF.DAILY.EMAIL.D13205       DPS001
PRDH.C.#NET.FTPSMF.DAILY.EMAIL.D13211       DPS001
PRDH.C.#NET.FTPSMF.DAILY.EMAIL.D13217       DPS001
PRDH.C.#NET.FTPSMF.DAILY.EMAIL.D13225       DPS001
PRDH.C.#NET.FTPSMF.DAILY.EMAIL.D13240       DPS001

```

# Batch

# Overview

---

- The next few slides will demonstrate how to code EZYEDIT in batch and execute the **SPACE** command
- Please view the [PDSMAN – PDSEASY](#) slide deck for more details on how to execute EZYEDIT in batch

# SPACE – Volume (⌚)

- List DASD volumes by name when usage is greater than 90%

```

Menu Utilities Compilers Help
-----
BROWSE      PRDSS.R2221.EZYEDIT.SPACE(SPACE01) - 01.02 Line 00000000 Col 001 080
Command ===>                                         Scroll ===> CSR
***** Top of Data *****
//SSSPACE JOB (SST), 'PDSEASY',MSGCLASS=T,CLASS=R,NOTIFY=&SYSUID
//-----*
///* PURPOSE: LIST DASD VOLUMES BY NAME AND GREATER THAN 90% USED
//-----*
//EZYEDIT EXEC PGM=PDSEASY
//EZYPRINT DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//SYSIN   DD *
    SPACE DPS*                                     /* DASD SPACE BY VOLUME */
    IF %USED GT 90                                 /* VOLUMES > 90% */
    HC                                              /* HARDCOPY REPORT */
***** Bottom of Data *****

```

# SPACE – Results

- **EZYPRINT** report after executing the commands

EZYEDIT Volume Information										
Volume	Cua	Cyls--Trks--Byts	Freespace	Free%	...25...	50...	75...	100	Cap	Cyls--Trks--Byts
DPS031	171C	6121 91887	5.21G	9%	**				55.7G	4112 61680
DPS034	23DB	5228 78633	4.46G	8%	**				55.7G	2736 41043
DPS035	239D	5290 79466	4.5G	8%	**				55.7G	2910 43650
DPS036	235B	5275 79290	4.49G	8%	**				55.7G	1636 24540
DPS037	231B	5823 87542	4.96G	9%	**				55.7G	2850 42755
DPS039	225B	5240 78727	4.46G	8%	**				55.7G	2148 32221
DPS040	229D	164 2610	148M	0%					55.7G	76 1154 65.4M

# SPACE – Address (Ø)

- List DASD volumes by control unit address (CUA)

```

Menu Utilities Compilers Help
-----
BROWSE      PRDSS.R2221.EZYEDIT.SPACE(SPACE02) - 01.03 Line 00000000 Col 001 080
Command ===>                                         Scroll ===> CSR
***** Top of Data *****
//@SSSPACE JOB (SST), 'PDSEASY',MSGCLASS=T,CLASS=R,NOTIFY=&SYSUID
//-----*
///* PURPOSE: LIST DASD VOLUMES BY CONTROL UNIT ADDRESS (CUA)
//-----*
//EZYEDIT EXEC PGM=PDSEASY
//EZYPRINT DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//SYSIN   DD *
    SPACE /171*                                     /* DASD SPACE BY CUA      */
    HC                                           /* HARDCOPY REPORT      */
***** Bottom of Data *****

```

# SPACE – Address – Results

- **EZYPRINT** report after executing the commands

EZYEDIT Volume Information										<--- Largest --->			
Volume	Cua	Volume Freespace					<--- Largest --->			Cap	Cyls	--Trks	--Byts
		Cyls	--Trks	--Byts	Free%	...25...	50...	75...	100	Cap	Cyls	--Trks	--Byts
DBW038	171F	6457	96869	5.49G	10%	**				55.7G	3742	56130	3.18G
DDL034	171B	9861	148K	8.38G	15%	***				55.7G	2913	43695	2.48G
DDL102	171A	5206	78135	4.43G	8%	**				55.7G	1700	25500	1.44G
DDL190	1713	5230	78623	4.46G	8%	**				55.7G	882	13230	750M
DDL250	1712	15786	237K	13.4G	24%	*****				55.7G	2500	37500	2.12G
DDL322	1711	3709	55647	3.15G	6%	**				55.7G	1099	16485	934M
DDL400	1710	4571	68580	3.89G	7%	**				55.7G	1760	26400	1.5G
DIMS54	1718	34075	512K	29G	52%	*****				55.7G	23088	346K	19.6G
DMD069	1715	20994	316K	17.9G	32%	*****				55.7G	4225	63375	3.59G
DPS031	171C	7207	108K	6.13G	11%	***				55.7G	4112	61692	3.5G
DSY062	171D	19879	298K	16.9G	30%	*****				55.7G	13096	196K	11.1G
DWRK33	171E	64515	968K	54.8G	98%	*****				55.7G	64429	966K	54.8G
ZAA1714	1714	65517	983K	55.7G	100%	*****				55.7G	65517	983K	55.7G
ZAA1716	1716	65517	983K	55.7G	100%	*****				55.7G	65517	983K	55.7G
ZAA1717	1717	65517	983K	55.7G	100%	*****				55.7G	65517	983K	55.7G
ZAA1719	1719	65517	983K	55.7G	100%	*****				55.7G	65517	983K	55.7G

# SPACE – Storage Group (Ø)

- List DASD volumes by storage group in descending order by usage when usage is greater than 90% used

```

Menu Utilities Compilers Help
-----
BROWSE      PRDSS.R2221.EZYEDIT.SPACE(SPACE03) - 01.05 Line 00000000 Col 001 080
Command ===>                                         Scroll ===> CSR
***** Top of Data *****
//@SSSPACE JOB (SST), 'PDSEASY',MSGCLASS=T,CLASS=R,NOTIFY=&SYSUID
//*-----*
///* PURPOSE: LIST VOLUMES BY STORAGE GROUP AND GREATER THAN 90% USED
//*-----*
//EZYEDIT EXEC PGM=PDSEASY
//EZYPRINT DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//SYSIN   DD *
SPACE SG=DPSPOL
SORT %USED D
IF %USED GT 90
HC
/* DASD SPACE BY STG GRP */
/* SORT %USED DESCENDING */
/* USED > 90% */
/* HARDCOPY REPORT */
***** Bottom of Data *****

```

# SPACE – Storage Group – Results

- **EZYPRINT** report after executing the commands

EZYEDIT Volume Information													
Volume	Cua	Tracks	Free	Used%	...25...	50...	75..	100	Vtoc#	Vtoc%	Ind	Ind#	Ind%
DPS034	23DB	983K	79969	92%	*****	*****	*****	*****	900	3%	Act	600	1%
DPS035	239D	983K	83463	92%	*****	*****	*****	*****	900	3%	Act	600	1%
DPS036	235B	983K	82229	92%	*****	*****	*****	*****	900	4%	Act	600	1%
DPS039	225B	983K	79676	92%	*****	*****	*****	*****	900	3%	Act	300	2%
DPS037	231B	983K	91767	91%	*****	*****	*****	*****	>1K	1%	Act	900	1%

# SPACE – Volume Summary (i)

- Display the **Volume Summary** report for particular DASD volumes

```

Menu Utilities Compilers Help
-----
BROWSE      PRDSS.R2221.EZYEDIT.SPACE(SPACE04) - 01.00 Line 00000000 Col 001 080
Command ===>                                         Scroll ===> CSR
***** Top of Data *****
//@SSSPACE JOB (SST), 'PDSEASY',MSGCLASS=T,CLASS=R,NOTIFY=&SYSUID
//*-----*
///* PURPOSE: DISPLAY 'VOLUME SUMMARY' FOR PARTICULAR DASD VOLUMES
//*-----*
//EZYEDIT EXEC PGM=PDSEASY
//EZYPRINT DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//SYSIN   DD *
    SPACE DPS*                                     /* DASD SPACE BY VOLUME */
    RIGHT TRK/CYL                                 /* VOLUME SUMMARY */
    HC                                           /* HARDCOPY REPORT */
***** Bottom of Data *****

```

# SPACE – Volume Summary – Results

- **EZYPRINT** report after executing the commands

EZYEDIT Volume Information									
<b>Volume Summary</b>									
Volume	Cua	Trk/Cyl	Tracks	Free	Frag	Device	Access	Mount	Status
DPS001	18DC	15	983K	354K	57	3390-9	DPSPOL	Private	Enabled
DPS002	18A3	15	983K	284K	47	3390-9	DPSPOL	Private	Enabled
DPS003	185C	15	983K	266K	16	3390-9	DPSPOL	Private	Enabled
DPS004	181C	15	983K	503K	47	3390-9	DPSPOL	Private	Enabled
DPS005	17DC	15	983K	240K	29	3390-9	DPSPOL	Private	Enabled
DPS006	17A1	15	983K	576K	13	3390-9	DPSPOL	Private	Enabled
DPS007	175C	15	983K	377K	9	3390-9	DPSPOL	Private	Enabled
DPS031	171C	15	983K	108K	126	3390-9	DPSPOL	Private	Enabled
DPS032	245B	15	983K	250K	110	3390-9	DPSPOL	Private	Enabled
DPS033	241B	15	983K	111K	157	3390-9	DPSPOL	Private	Enabled
DPS034	23DB	15	983K	79969	159	3390-9	DPSPOL	Private	Enabled
DPS035	239D	15	983K	83463	127	3390-9	DPSPOL	Private	Enabled
DPS036	235B	15	983K	82229	178	3390-9	DPSPOL	Private	Enabled
DPS037	231B	15	983K	91767	146	3390-9	DPSPOL	Private	Enabled
DPS038	22DB	15	983K	162K	119	3390-9	DPSPOL	Private	Enabled
DPS039	225B	15	983K	79676	117	3390-9	DPSPOL	Private	Enabled

# SPACE – Volume Space (①)

- Display the Volume Space report for particular DASD volumes

```

Menu Utilities Compilers Help
-----
BROWSE      PRDSS.R2221.EZYEDIT.SPACE(SPACE05) - 01.01 Line 00000000 Col 001 080
Command ===>                                         Scroll ===> CSR
***** Top of Data *****
//@SSSPACE JOB (SST), 'PDSEASY',MSGCLASS=T,CLASS=R,NOTIFY=&SYSUID
//-----*
///* PURPOSE: DISPLAY 'VOLUME SPACE' FOR PARTICULAR DASD VOLUMES
//-----*
//EZYEDIT EXEC PGM=PDSEASY
//EZYPRINT DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//SYSIN   DD *
    SPACE DPS*                                     /* DASD SPACE BY VOLUME */
    RIGHT TOTCYL                                 /* VOLUME SPACE */
    HC                                           /* HARDCOPY REPORT */
***** Bottom of Data *****

```

# SPACE – Volume Space – Results

- **EZYPRINT** report after executing the commands

EZYEDIT Volume Information											
Volume	Cua	Volume Space									
		T-Cyl	T-Trk	T-Byt	F-Cyl	F-Trk	F-Byt	F-Ext	L-Cyl	L-Trk	L-Byt
DPS001	18DC	65520	983K	55.7G	23576	354K	20.1G	35	17585	264K	15G
DPS002	18A3	65520	983K	55.7G	18912	284K	16.1G	22	15373	231K	13.1G
DPS003	185C	65520	983K	55.7G	17701	266K	15.1G	23	17041	256K	14.5G
DPS004	181C	65520	983K	55.7G	33508	503K	28.5G	28	25069	376K	21.3G
DPS005	17DC	65520	983K	55.7G	15994	240K	13.6G	26	14762	221K	12.6G
DPS006	17A1	65520	983K	55.7G	38364	576K	32.6G	15	37198	558K	31.6G
DPS007	175C	65520	983K	55.7G	25136	377K	21.4G	24	24639	370K	20.9G
DPS031	171C	65520	983K	55.7G	7207	108K	6.13G	17	4112	61692	3.5G
DPS032	245B	65520	983K	55.7G	16631	250K	14.1G	34	6492	97382	5.52G
DPS033	241B	65520	983K	55.7G	7382	111K	6.29G	56	2597	38955	2.21G
DPS034	23DB	65520	983K	55.7G	5304	79969	4.53G	81	2736	41043	2.33G
DPS035	239D	65520	983K	55.7G	5558	83463	4.73G	26	2910	43650	2.47G
DPS036	235B	65520	983K	55.7G	5466	82229	4.66G	43	1636	24540	1.39G
DPS037	231B	65520	983K	55.7G	6098	91767	5.2G	39	2850	42755	2.42G
DPS038	22DB	65520	983K	55.7G	10805	162K	9.19G	28	4788	71828	4.07G
DPS039	225B	65520	983K	55.7G	5301	79676	4.51G	32	2148	32221	1.83G

# SPACE – USAGE (⌚)

- Display the **USAGE** report for particular DASD volumes

```

Menu Utilities Compilers Help
-----
BROWSE      PRDSS.R2221.EZYEDIT.SPACE(SPACE06) - 01.01 Line 00000000 Col 001 080
Command ===>                                         Scroll ===> CSR
***** Top of Data *****
//@SSSPACE JOB (SST), 'PDSEASY',MSGCLASS=T,CLASS=R,NOTIFY=&SYSUID
//-----*
///* PURPOSE: DISPLAY 'USAGE' REPORT FOR PARTICULAR DASD VOLUMES
//-----*
//EZYEDIT EXEC PGM=PDSEASY
//EZYPRINT DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//SYSIN   DD *
    SPACE DPS*                                     /* DASD SPACE BY VOLUME */
    USAGE                                           /* USAGE REPORT */
    HC                                             /* HARDCOPY REPORT */
***** Bottom of Data *****

```

# SPACE – USAGE – Results

- **EZYPRINT** report after executing the commands

```

Display Filter View Print Options Search Help
-----
SDSF OUTPUT DISPLAY @SSSPACE J0118654 DSID 102 LINE 0 COLUMNS 02- 81
COMMAND INPUT ===> SCROLL ==> CSR
***** TOP OF DATA *****
01-June-2015 At 15:35 DV21 EZYEDIT Utility Report
Storage Usage Summary

Total Tracks= 16,711,000 Free= 3,840,104 Usage= 77%

Volume(s) processed : 17
01-June-2015 At 15:35 DV21 EZYEDIT Volume Information
----- Volume Freespace -----> <--- Largest --->
Volume Cua Cyls--Trks--Byts Free% ...25...50...75..100 Cap Cyls--Trks--Byts
DPS001 18DC 23576 354K 20.1G 36% ***** 55.7G 17585 264K 15G
DPS002 18A3 18912 284K 16.1G 29% ***** 55.7G 15373 231K 13.1G
DPS003 185C 17701 266K 15.1G 27% ***** 55.7G 17041 256K 14.5G
DPS004 181C 33508 503K 28.5G 51% ***** 55.7G 25069 376K 21.3G
DPS005 17DC 15994 240K 13.6G 24% ***** 55.7G 14762 221K 12.6G
DPS006 17A1 38364 576K 32.6G 59% ***** 55.7G 37198 558K 31.6G
DPS007 175C 25136 377K 21.4G 38% ***** 55.7G 24639 370K 20.9G
DPS031 171C 7207 108K 6.13G 11% *** 55.7G 4112 61692 3.5G

```

# Links

# PDSMAN

## Links

[PDSMAN – EZYEDIT – Introduction](#)

[PDSMAN – EZYEDIT – Selection Panel](#)

[PDSMAN – EZYEDIT – Dataset List](#)

[PDSMAN – EZYEDIT – Member List](#)

[PDSMAN – EZYEDIT – SPACE](#)

[PDSMAN – EZYEDIT – TSO Command Shell](#)

[PDSMAN – Introduction](#)

[PDSMAN – Member Versions](#)

[PDSMAN – FASTCOPY](#)

[PDSMAN – PDSEASY](#)

[PDSMAN – PDSM18](#)

[PDSMAN – PDSMURPT](#)

# Other

## Links

- [ISPF – An Experienced User Shares His Secrets](#)
- [ISPF – Workstation Agent \(WSA\)](#)
- [OPSMVS – OPSLOG Overview](#)
- [REXX and ISPF – Troubleshooting](#)
- [SDSF – Beyond the Basics](#)

# Conclusion

# Final Comments

- PDSMAN provides a wide range of solutions to PDS and PDSE issues users face on a daily basis
  - Saves time and increases productivity
- Every PDSMAN/EZYEDIT release introduces new features and commands which are easy to understand, implement and use
- The tutorials and manuals are exceptional
  - Easy to read and understand
  - Suggest downloading the manuals periodically to obtain new updates

# Thank You!

- A special thank you to the CA PDSMAN team for their technical input and assistance
- Suggest checking out the CA PDSMAN community web site at:  
[CA – Mainframe Community – PDSMAN](#)

Or

[CA – Mainframe Community](#)

Select ‘**CA PDSMAN PDS Library Management**’ from the ‘**Products Covered**’ section located on the left hand side of the web page



*Any questions or comments please contact*

*Bruce Koss*

*Wells Fargo Mainframe Operating Systems Support*

*[Bruce.Koss@WellsFargo.com](mailto:Bruce.Koss@WellsFargo.com)*

*(704) 600-8416*



#SHAREorg



**SHARE is an independent volunteer-run information technology association  
that provides education, professional networking and industry influence.**

