


Introduction to IPCS for Application Programmers

Thomas Petrolino
IBM Poughkeepsie
tapetro@us.ibm.com



Trademarks

The following are trademarks of the International Business Machines Corporation in the United States and/or other countries.

Language Environment

z/OS

CICS

* Registered trademarks of IBM Corporation

The following are trademarks or registered trademarks of other companies.

Java and all Java-related trademarks and logos are trademarks of Sun Microsystems, Inc., in the United States and other countries.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows and Windows NT are registered trademarks of Microsoft Corporation.

UNIX is a registered trademark of The Open Group in the United States and other countries.

SET and Secure Electronic Transaction are trademarks owned by SET Secure Electronic Transaction LLC.

* All other products may be trademarks or registered trademarks of their respective companies.

Notes:

Performance is in Internal Throughput Rate (ITR) ratio based on measurements and projections using standard IBM benchmarks in a controlled environment. The actual throughput that any user will experience will vary depending upon considerations such as the amount of multiprogramming in the user's job stream, the I/O configuration, the storage configuration, and the workload processed. Therefore, no assurance can be given that an individual user will achieve throughput improvements equivalent to the performance ratios stated here.

IBM hardware products are manufactured from new parts, or new and serviceable used parts. Regardless, our warranty terms apply.


All customer examples cited or described in this presentation are presented as illustrations of the manner in which some customers have used IBM products and the results they may have achieved. Actual environmental costs and performance characteristics will vary depending on individual customer configurations and conditions.

This publication was produced in the United States. IBM may not offer the products, services or features discussed in this document in other countries, and the information may be subject to change without notice. Consult your local IBM business contact for information on the product or services available in your area.

All statements regarding IBM's future direction and intent are subject to change or withdrawal without notice, and represent goals and objectives only.


Information about non-IBM products is obtained from the manufacturers of those products or their published announcements. IBM has not tested those products and cannot confirm the performance, compatibility, or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

Prices subject to change without notice. Contact your IBM representative or Business Partner for the most current pricing in your geography.




Agenda

- IPCS Overview
- Capturing a Dump
- A Guided Tour
 - Initializing A Dump
 - Status
 - Browsing Storage
 - Address Spaces and Tasks
 - Other Interesting Commands
- Sources of Additional Information




IPCS Overview




IPCS Overview

- **Interactive Problem Control System (IPCS)**
 - **Formatting and analysis support for**
 - Unformatted dumps (SVC, Console, SYSMDUMP, transaction, stand-alone)
 - Traces (GTF, component, master console, system)
 - **Several different interfaces**
 - Line / Batch / Dialog mode
 - Most popular is full screen (dialog) mode run under ISPF




IPCS Overview...

- Advantages over Formatted Dump
 - Provides a more complete picture of the problem
 - Powerful commands and formatters available for dump analysis
- Disadvantages
 - Additional skills required for analysis
 - Application programmers may not have access to system dumps and/or IPCS




Capturing a Dump




Capturing a Dump

- System Mechanisms
 - SLIP, SVC, Console Dumps
 - Not usually available to Application Programmers
- Language Environment Mechanisms
 - TERMTHDACT Run-time Option is used to request a dump for an unhandled condition of severity 2 or greater
 - Suboption UADUMP/UATRACE/UAONLY
 - Application can use CEE3ABD callable service to request a dump while terminating
 - Type of dump controlled using TERMTHDACT setting




Capturing a Dump...

- TERMTHDACT Run-time Option not Sufficient
 - Application must also either:
 - Allocate a SYSMDUMP DD
 - SYSMDUMP DD DSN=<dump name>, SPACE=(CYL,(200,200),RLSE),DISP=(NEW,DELETE, CATLG),DCB=(RECFM=FBS,DSORG=PS,LRECL=4160, BLKSIZE=24960),UNIT=SYSDA
 - Not always convenient to add to JCL or to execution environment
 - Or, specify the DYNDUMP Run-time Option...




Capturing a Dump...

- DYNDUMP run-time option
 - DYNDUMP(hlq,U4039-ABEND,U40xx-ABEND)
 - hlq
 - *USERID or *USERID.hlq
 - *TSOPREFIX or *TSOPRE
 - (also *TSOPREFIX.hlq or *TSOPRE.hlq)
 - Up to 26 characters of an MVS data set name




Capturing a Dump...

- DYNDUMP run-time option
 - DYNDUMP(hlq,U4039-ABEND,U40xx-ABEND)
 - U4039-ABEND
 - NODYNAMIC (default)
 - DYNDUMP turned off for U4039 ABENDs
 - DYNAMIC
 - DYNDUMP active for U4039 ABENDs if no SYSMDUMP, SYSUDUMP or SYSABEND DD.
 - FORCE
 - DYNDUMP active for U4039 ABENDs even with above DDs allocated
 - BOTH
 - DYNDUMP plus SYSMDUMP/SYSUDUMP/SYSABEND



Capturing a Dump...

- DYNDUMP run-time option
 - DYNDUMP(hlq,U4039-ABEND,U40xx-ABEND)
 - U40xx-ABEND
 - TDUMP (Default)
 - DYNDUMP is active for all U40xx ABENDs (other than U4039) which request a dump.
 - NoTDUMP
 - DYNDUMP is not active for U40xx ABENDs



Capturing a Dump...


```
+CEE3798I ATTEMPTING TO TAKE A DUMP FOR ABEND U4039 TO
DATA SET: PETRO.D194.T0904332.INTIPCS

IGD101I SMS ALLOCATED TO DDNAME (SYS00001) 084
      DSN (PETRO.D194.T0904332.INTIPCS )
      STORCLAS (STANDARD) MGMTCLAS (MIGONLY) DATACLAS ( )
      VOL SER NOS= SL7330


IGD104I PETRO.D194.T0904332.INTIPCS
      RETAINED, DDNAME=SYS00001

IEA822I COMPLETE TRANSACTION DUMP WRITTEN TO
      PETRO.D194.T0904332.INTIPCS

+CEE3797I LANGUAGE ENVIRONMENT HAS DYNAMICALLY CREATED A
DUMP .
```



A Guided Tour



The Main IPCS Panel

```
----- IPCS PRIMARY OPTION MENU -----  
OPTION ===>  
  
0  DEFAULTS      - Specify default dump and options  
1  BROWSE        - Browse dump data set  
2  ANALYSIS       - Analyze dump contents  
3  UTILITY        - Perform utility functions  
4  INVENTORY      - Inventory of problem data  
5  SUBMIT         - Submit problem analysis job to batch  
6  COMMAND        - Enter subcommand, CLIST or REXX exec  
T  TUTORIAL       - Learn how to use the IPCS dialog  
X  EXIT           - Terminate using log and list defaults  
  
Enter END command to terminate IPCS dialog
```

Initializing the Dump

- Use IPCS Option 0 to tell IPCS which dump to process

```
----- IPCS Default Values -----
```

Command ==>

You may change any of the defaults listed below. The defaults shown before any changes are LOCAL. Change scope to GLOBAL to display global defaults.

Scope ==> BOTH (LOCAL, GLOBAL, or BOTH)

If you change the Source default, IPCS will display the current default Address Space for the new source and will ignore any data entered in the Address Space field.

Source ==> DSNAME('PETRO.D194.T0904332.INTIPCS')

Address Space ==>

Message Routing ==> NOPRINT TERMINAL NOPDS

Message Control ==> CONFIRM VERIFY FLAG(TERMINATING)

Display Content ==> MACHINE REMARK REQUEST NOSTORAGE SYMBOL


Press ENTER to update defaults.

Initializing the Dump...

- Issue an IPCS command to cause IPCS to initialize the dump

```
----- IPCS PRIMARY OPTION MENU -----  
OPTION ===> ip status faildata  
 0 DEFAULTS      - Specify default dump and options  
 1 BROWSE        - Browse dump data set  
 2 ANALYSIS      - Analyze dump contents
```


```
IKJ56650I TIME-10:11:37 AM. CPU-00:00:01 SERVICE-53266 SESSION-01:13:40 JULY  
BLS18122I Initialization in progress for DSNAME('PETRO.D194.T0904332.INTIPCS')  
BLS18124I TITLE=JOBNAME INTIPCS STEPNAME G                         USER 4039  
BLS18223I Dump written by z/OS 01.13.00 SYSMDUMP - level same as IPCS level  
BLS18222I z/Architecture mode system  
BLS18160D May summary dump data be used by dump access? Enter Y to use, N to  
          bypass.  
Y  
BLS18123I 16,260 blocks, 67,641,600 bytes, in DSNAME('PETRO.D194.T0904332.INT  
IKJ56650I TIME-10:11:44 AM. CPU-00:00:01 SERVICE-56368 SESSION-01:13:48 JULY  
BLS18224I Dump of z/OS 01.13.00 - level same as IPCS level  
***
```



IPCS Status Command

```
* * * DIAGNOSTIC DATA REPORT * * *
SEARCH ARGUMENT ABSTRACT
RIDS/CEEPLPKA#L RIDS/#UNKNOWN AB/U4039 PRCS/00000000 REGS/0B0DA REGS/05000

Symptom                                Description
-----
RIDS/CEEPLPKA#L      Load module name: CEEPLPKA
RIDS/#UNKNOWN        Csect name: #UNKNOWN
AB/U4039              User Abend code: 4039
PRCS/00000000         Abend reason code: 00000000
REGS/0B0DA            Register/PSW difference for R0B: 0DA
REGS/05000             Register/PSW difference for R05: 000
...
```



IPCS Status Command...

...

Time of Error Information

PSW: 07851000 80000000 00000000 20FEF8B2

Instruction length: 02 Interrupt code: 000D

Failing instruction text: 00181610 0A0D58D0 D00498EC

Breaking event address: 00000000_00000000

AR/GR 0-1 00000000/00000000_84000000 00000000/00000000_84000**FC7**

AR/GR 2-3 00000000/00000000_2111D9A8 00000000/00000000_00040004

AR/GR 4-5 00000000/00000000_20FE3FA0 00000000/00000000_20FEF8B2

AR/GR 6-7 00000000/00000000_20F0E348 00000000/00000000_20F0B448

AR/GR 8-9 00000000/00000000_2111D9A8 00000000/00000000_2111D53C

AR/GR 10-11 00000000/00000000_2111E0AF 00000000/00000000_A0FEF7D8


AR/GR 12-13 00000000/00000000_20F0FBEO 00000000/00000000_211201A8

AR/GR 14-15 00000000/00000000_A0FE3070 00000000/7FFC8400_00000000

Home ASID: 014B Primary ASID: 014B Secondary ASID: 014B


PKM: 00C0 AX: 0000 EAX: 0000

This Task's ASID/TCB: 014B/008D89F0




IPCS Browse

- Option 1 on the IPCS Primary Options Panel
 - Allows user to browse raw storage in the dump
 - Maintains a handy list of user-defined pointers
 - To access, specify 1 on the Primary Options Panel, and then hit <enter> on the next panel




IPCS Browse...

```
DSNAME ('PETRO.D194.T0904332.INTIPCS') POINTERS -----
Command ===>                                                 SCROLL ===> CSR
ASID(X'014B') is the default address space
PTR   Address          Address space          Data type
00001 00.            ASID(X'014B')          AREA
Remarks:
***** END OF POINTER STACK *****
```



IPCS Browse...

- Pointer Stack Panel – Line Commands
 - Entered by typing over pointer number
 - S – Select a pointer entry for browsing
 - F – Format pointer entry storage
 - I – Insert a pointer entry
 - D – Delete a pointer entry
 - R – Repeat a pointer entry
 - E – Edit a pointer entry




IPCS Browse...

```
DSNAME ('PETRO.D194.T0904332.INTIPCS') POINTERS -----
Command ==>                                                 SCROLL ==> CSR
ASID(X'014B') is the default address space
PTR   Address          Address space          Data type
      s0001 00.           ASID(X'014B')        AREA
Remarks:
***** END OF POINTER STACK *****
```

IPCS Browse...

ASID(X'014B') ADDRESS(00.) STORAGE -----					SCROLL ==> CSR
Command ==>					
00000000	000A0000	000130E1	00000000	00000000
00000010	00FD46B0	00000000	7FFFF000	7FFFF000 ".0.".0.
00000020	7FFF0000	7FFF0000	7FFF0000	7FFF0000	".0.".0.".0.".0.
00000030	00000000	00000000	7FFF0000	7FFF0000 ".0.".0.
00000040	00000000	00000000	00000000	00FD46B0
00000050	00000000	00000000	000A0000	000140E1
00000060	000A0000	000150E1	000A0000	000160E1 & -
00000070	000A0000	000170E1	000A0000	000180E1
00000080	00000000	00001005	00020001	00040016
00000090	00000002	00000000	00000000	00000000
000000A0	0A004201	014CD308	00000048	0230B400 <L.
000000B0	00000000	00000000	000108A4	00E1A0E8 u . . Y
000000C0	28000000	00000000	FBF7FFF8	FCFF0802 7 . . .
000000D0	781C0000	00000000	00000000	00000000
000000E0	.:010F.--	All bytes contain X'00'			



IPCS Browse...

- Many ISPF-like Browse commands work
 - PF7|PF8 page up|down
 - PF3 return
 - UP|DOWN n scroll up|down n lines
 - FIND (more later)
 - PF5 Repeat Find

IPCS Browse...

- Locate command – Used to jump to another address

```
ASID(X'014B') ADDRESS(00.) STORAGE -----
Command ===> l 20F0FBEO                               SCROLL ===> CSR
00000000 000A0000 000130E1 00000000 00000000 | ..... . . . . .
00000010 00FD46B0 00000000 7FFFF000 7FFFF000 | ..... " . . . . .
00000020 7FFF000 7FFF000 7FFF000 7FFF000 | ". . . . " . . . . .
00000030 00000000 00000000 7FFF000 7FFF000 | ..... " . . . . .
00000040 00000000 00000000 00000000 00FD46B0 | ..... . . . . .
00000050 00000000 00000000 000A0000 000140E1 | ..... . . . . .
00000060 000A0000 000150E1 000A0000 000160E1 | ..... & . . . - .
00000070 000A0000 000170E1 000A0000 000180E1 | ..... . . . . .
00000080 00000000 00001005 00020001 00040016 | ..... . . . . .
00000090 00000002 00000000 00000000 00000000 | ..... . . . . .
000000A0 0A004201 014CD308 00000048 0230B400 | ..... <L . . . . .
000000B0 00000000 00000000 000108A4 00E1A0E8 | ..... . u . . Y .
000000C0 28000000 00000000 FBF7FFF8 0CFF0802 | ..... . 7 . . . .
000000D0 781C0000 00000000 00000000 00000000 | ..... . . . . .
000000E0..:010F.--All bytes contain X'00'
```

IPCS Browse...

- X – Symbol representing current location in dump

```
ASID(X'014B') ADDRESS(20F0FBEO.) STORAGE -----
Command ==> l x-18                                         SCROLL ==> CSR
20F0FBEO 00000800 00000000 2111D018 2113D018 | .....}....}.. |
20F0FBF0.:20F0FC4F.--All bytes contain X'00'
20F0FC50 00000000 800114E0 00000000 00000000 | .....\\..... |
20F0FC60.:20F0FCFF.--All bytes contain X'00'
20F0FD00 20F09F98 00000000 00000000 00000000 | .0.q..... |
20F0FD10.:20F0FD6F.--All bytes contain X'00'
20F0FD70 00000000 00000000 50C0D064 0DC058C0 | .....&{ }..{.{ |
20F0FD80 C0060DCC 0000992C 0700C3C8 0700C3C8 | {.....r...CH..CH |
20F0FD90 0700C3C8 0700C3C8 0700C3C8 0700C3C8 | ..CH..CH..CH..CH |
20F0FDA0.:20F0FDBF.--Same as above
20F0FDC0 0700C3C8 0700C3C8 0700C3C8 00000000 | ..CH..CH..CH.... |
20F0FDD0.:20F0FE2F.--All bytes contain X'00'
20F0FE30 00000000 00000000 00000000 20F09760 | .....0p- |
20F0FE40 00000000 00000000 8000E420 8000E340 | .....U...T |
20F0FE50.:20F0FE7F.--All bytes contain X'00'
```

IPCS Browse...


```
ASID(X'014B') ADDRESS(20F0FBC8.) STORAGE -----
Command ==>                                                 SCROLL ==> CSR
20F0FBC8                               C3C5C5C3   C1C14040 |       CEECAA    |
20F0FB0D0 00000000 00000000 000058C0 D0640CCC | .....{ }... |
20F0FB0E0 00000800 00000000 2111D018 2113D018 | .....}...}. |
20F0FB0F..:20F0FC4F.--All bytes contain X'00'
20F0FC50 00000000 800114E0 00000000 00000000 | .....\\..... |
20F0FC60..:20F0FCFF.--All bytes contain X'00'
20F0FD00 20F09F98 00000000 00000000 00000000 | .0.q..... |
20F0FD10..:20F0FD6F.--All bytes contain X'00'
20F0FD70 00000000 00000000 50C0D064 0DC058C0 | .....&{ }..{. |
20F0FD80 C0060DCC 0000992C 0700C3C8 0700C3C8 | {.....r...CH..CH |
20F0FD90 0700C3C8 0700C3C8 0700C3C8 0700C3C8 | ..CH..CH..CH..CH |
20F0FDA0..:20F0FDBF.--Same as above
20F0FDC0 0700C3C8 0700C3C8 0700C3C8 00000000 | ..CH..CH..CH.... |
20F0FDD0..:20F0FE2F.--All bytes contain X'00'
```

IPCS Browse...

- Stack command – saves address on the pointer list

```
DSNAME ('PETRO.D194.T0904332.INTIPCS') POINTERS -----
Command ==> ip stack 20F0FBEO                                     SCROLL ==> CSR
ASID(X'014B') is the default address space
PTR   Address          Address space                         Data type
00001 00.              ASID(X'014B')                      AREA
Remarks:
***** END OF POINTER STACK *****
```

```
DSNAME ('PETRO.D194.T0904332.INTIPCS') POINTERS -----
Command ==>                                                 SCROLL ==> CSR
ASID(X'014B') is the default address space
PTR   Address          Address space                         Data type
00001 00.              ASID(X'014B')                      AREA
Remarks:
00002 20F0FBEO.        ASID(X'014B')                      AREA
Remarks: CAA Pointer
***** END OF POINTER STACK *****
```



IPCS Browse...


- Word Selection when browsing storage
 - Selection codes used with the storage panel allows a user to treat storage contents as addresses
 - L - Interpret the word as a 24-bit address and stack it
 - H - Interpret the word as a 31-bit address and stack it
 - % - Interpret the word as a 24-bit address, stack it, and display the addressed storage
 - ? - Interpret the word as a 31-bit address, stack it, and display the addressed storage
 - ! - Interpret the double word as a 64-bit address, stack it, and display the addressed storage

IPCS Browse...

```
ASID(X'014B') ADDRESS(20F0FBEO.) STORAGE -----
Command ==>                                                 SCROLL ==> CSR
20F0FBEO    00000800    00000000 ? 2111D018    2113D018    | .....}....|. |
20F0FBF0.:20F0FC4F.--All bytes contain X'00'
```


```
ASID(X'014B') ADDRESS(2111D018.) STORAGE -----
Command ==>                                                 SCROLL ==> C
2111D018                      E2E3D2E4    20F10454    |           STKU.1.. |
2111D020    20F10454    00020000    00000000    00000000    | .1.....|. |
2111D030    00000000    20F10688    2111D4B0    A110761A    | .....1.h..M.~...|
```

```
DSNAME ('PETRO.D194.T0904332.INTIPCS') POINTERS -----
Command ==>                                                 SCROLL ==> CSR
ASID(X'014B') is the default address space
...
00002 20F0FBEO.          ASID(X'014B')          AREA
  Remarks: CAA Address
00003 2111D018.          ASID(X'014B')          AREA
  Remarks:
```




IPCS Browse...

- Finding specific values in storage
 - Use the FIND command
 - Entered on the command line of any storage browse panel
 - find ccc – locates an EBCDIC string
ex: find ceecaa
 - find x'xxxx' – locates a hexadecimal value
ex: find x' 47f0f014'
 - find * - uses the same find value as the previous find command
 - find first / last / next / prev
 - find nobreak (or nbr) – tells IPCS to continue processing if it cannot retrieve storage from the dump
 - Can also specify storage boundary, column boundary, mask value, data length, ASCII data...




IPCS Browse...

- EQUATE command - Allows a user to create a symbol with an associated address and attributes
 - Syntax: EQUATE/EQU/EQ name <addr>
ex: ip equ caa 20F0FBE0
 - Symbol can be used in places where an address may be specified
ex: l caa




IPCS Browse...

- EQUATE command...
 - Use “equate *name*” without providing an address to assign the value of “X” (current location) to the specified symbol name
 - Use LISTSYM command to show all defined equates
 - The list will be long, since IPCS defines many equates on its own
 - Use “dropsym *name* purge” to delete a symbol



IPCS Browse...


```
IPCS OUTPUT STREAM ----- Line 336 Cols 1 7
Command ===> SCROLL ===> CSR
ASCB335      F75880. ASID(X'0001') LENGTH(X'0180') STRUCTURE(Ascb) NODROP
ASVT         FABDA8. ASID(X'0001') POSITION(X'+01E0') LENGTH(X'2074')
              STRUCTURE(Asvt) NODROP
ASXB331      8FDB60. ASID(X'014B') LENGTH(X'0300') STRUCTURE(Asxb) NODROP
CAA          20F0FBE0. ASID(X'014B') LENGTH(X'04') AREA DROP
COMMON        900000. ASID(X'0001') LENGTH(X'700000') AREA(Common) NODROP
COMPONENTID   00. LITERAL LENGTH(X'09') CHARACTER NODROP
CVT          FD46B0. ASID(X'0001') POSITION(X'-28') LENGTH(X'0528')
              STRUCTURE(Cvt) NODROP
CVTXTNT2     FD4C10. ASID(X'0001') LENGTH(X'84') STRUCTURE(Cvtxtnt2) NODROP
DAESYMPTOMS  00. LITERAL LENGTH(X'54') CHARACTER NODROP
DSA001        211201A8. ASID(X'014B') LENGTH(X'04') AREA DROP
DSA002        2111D0B0. ASID(X'014B') LENGTH(X'04') AREA DROP
DSA003        2111D030. ASID(X'014B') LENGTH(X'04') AREA DROP
DSA004        20F10688. ASID(X'014B') LENGTH(X'04') AREA DROP
DSA005        6008. ASID(X'014B') LENGTH(X'04') AREA DROP
DUMPINGPROGRAM 00. LITERAL LENGTH(X'08') CHARACTER NODROP
```



IPCS Browse...


- List command - Displays storage in the dump
 - Boring by itself, but by adding INST attribute, IPCS will disassemble instructions at the given address
 - ip list 20f00072 len(24) inst :

```
IPCS OUTPUT STREAM -----
Command ===>
*****
LIST 20F00072. ASID(X'014B') LENGTH(X'18') INSTRUCTION
ASID(X'014B') ADDRESS(20F00072.) KEY(88)
20F00072 | 1812           | LR      R1,R2
20F00074 | C0B0 FFFF FFC6 | LARL    R11,*-X'74'
20F0007A | 1744           | XR      R4,R4
20F0007C | 5010 4000       | ST      R1,X'0'(,R4)
20F00080 | 4110 B08C       | LA      R1,X'8C'(,R11)
20F00084 | 58F0 B0A0       | L       R15,X'A0'(,R11)
20F00088 | 05EF           | BALR    R14,R15
*****
```



IPCS Summary Command

- Produces information associated with an address space
 - Defaults to current ASID, but user can identify other(s) to work with using ASIDLIST, JOBLIST, JOBNAME keywords
- summary format (or summ format)
 - produces detailed report of major control blocks in the address space
 - ASCB / ASSB
 - TCBs / STCBs / RBs
 - RTM2WA
 - Load Lists / Job Pack Queue
 - Linkage stacks / Save Areas
 - TCB Summary




IPCS Summary Command...

- TCB Summary
 - Found at the end of the Summary output

```
* * * * * T C B S U M M A R Y * * * * *

JOB INTIPCS ASID 014B ASCB 00F75E80 FWDP 00F75D00 BWDP 00F76100 PAGE
00000017

    TCB   AT     CMP      NTC      OTC      LTC      TCB      BACK      PAGE
008FE040 00000000 00000000 00000000 008FF890 008FD0C0 00000000 00000057
008FD0C0 00000000 00000000 008FE040 00000000 008FF890 008FE040 00000063
008FF890 00000000 008FD0C0 008FE040 008FF260 008FF260 008FD0C0 00000067
008FF260 00000000 00000000 008FF890 008D89F0 008D89F0 008FF890 00000074
008D89F0 84000FC7 00000000 008FF260 00000000 00000000 008FF260 00000082
```



IPCS Summary Command...

■ TCB/STCB/RB Information

TCB: 008D89F0


+0000	RBP.....	008FD548	PIE.....	000060A0	DEB.....	008C9048
+000C	TIO.....	008CFFD0	CMP.....	84000FC7	TRN.....	00000000
+0018	MSS.....	7F4BE958	PKF.....	80	FLGS.....	00000000 00
+0022	LMP.....	FF	DSP.....	FF	LLS.....	008FDF90
+0028	JLB.....	008D98E8	JPQ.....	008FFA18		

General purpose register values

0-3	7F4A9840	000007C0	086782D0	7F43EE70
4-7	7F458640	00003B5F	00001040	7F440E60
8-11	7F43FC50	00020003	7F456DE8	00003B5E
12-15	0B3F8AA0	00000008	03C4C000	000007C0

64-Bit GPRs from TCB/STCB

0-1	00000000_7F4A9840	00000000_000007C0
2-3	00000048_086782D0	00000000_7F43EE70
4-5	00000048_7F458640	00000000_00003B5F
6-7	00000000_00001040	00000000_7F440E60
8-9	00000000_7F43FC50	00000048_00020003



IPCS Summary Command...

■ RTM2WA Information

RTM2WA SUMMARY

```
+001C Completion code           84000FC7
+008C Abending program name/SVRB address GO
+0094 Abending program addr      20F00000

      GPRs at time of error
 0-3  84000000  84000FC7  2111D9A8  00040004
 4-7  20FE3FA0  20FEF8B2  20F0E348  20F0B448
 8-11 2111D9A8  2111D53C  2111E0AF  A0FEF7D8
 12-15 20F0FBEO  211201A8  A0FE3070  00000000

+06D8 PSW at time of error: 07851000 80000000 00000000 20FEF8B2
+0084 Instruction Length Code: 0002  Interruption Code: 000D
+06C8 Translation Exception Identification: 00000000 00000000
+00DC SDWACOMP                 00000000
+00E8 Return code from recovery routine-00
      Continue with termination-implies percolation
+00E0 Retry Address returned from recovery exit 00000000
```

IPCS Summary Command...

■ Load List

```
EP..... CEEMENU3
ENTPT.... A1149000 RRBP..... 00000000 USE..... 0001 SP..... FC
Reenterable. Reusable.
LOADCNT.. 0001 SYSCT.... 0000
NRFAC.... 00000001 MSBAD.... 21149000 LNTH..... 0000C810
NAMEL.... 0008 ASID..... 014B PROVIDI.. 00000002
PROVIDD.. 00000000 00D31200 E2E3C5D7 D3C9C240
EPTOKEN.. 00000C3E 014B001F


EP..... CEEPLPKA
ENTPT.... A0F11000 RRBP..... 00000000 USE..... 0001 SP..... FC
Reenterable. Reusable.
LOADCNT.. 0001 SYSCT.... 0000
NRFAC.... 00000001 MSBAD.... 20F11000 LNTH..... 00207110
NAMEL.... 0008 ASID..... 014B PROVIDI.. 00000002
PROVIDD.. 00000000 05020800 E2E3C5D7 D3C9C240
EPTOKEN.. 00000C3D 014B004D
```

IPCS Summary Command...

■ Linkage Stack Entry

```
LINKAGE STACK ENTRY 00 FROM TCB. LSED: 7F495010
LSEH: 7F495000
FNXT..... 00000000 BSEA..... 00000000 TYPE..... 89
HEADER ENTRY
RFS..... 0FD0 NES..... 0128

LINKAGE STACK ENTRY 01 FROM TCB. LSED: 7F495138
LSE: 7F495018
GENERAL PURPOSE REGISTER VALUES
00-01.... 00000000 0B3A9068 00000000 A0F0B200
02-03.... 00000000 A0F0B200 00000000 0000E670
...
PKM..... 00C0 SASN..... 014B SINS..... 00000001
EAX..... 0000 PASN..... 014B PINS..... 00000001
PSW..... 07043000 80000000 PSWE..... 00000000 0B3A61C4
TARG..... 00000000 8B3E1B42 MSTA..... 00000000 00000000
TYPE..... 8C
```




Where Command

- Identifies an area at a given address
 - where 20f00080

```
ASID(X'014B') 20F00080. AREA(Subpool251Key08)+80 IN EXTENDED PRIVATE  
ASID(X'014B') 20F00080. GO+80 IN EXTENDED PRIVATE
```

- where 20fef8b2

```
ASID(X'014B') 20FEF8B2. AREA(Subpool252Key00)+0DE8B2 IN EXTENDED PRIVATE  
ASID(X'014B') 20FEF8B2. CEEPLPKA+0DE8B2 IN EXTENDED PRIVATE
```




Master Trace

■ Option 2.7.3

- Formats the master trace table, containing the most recently issued console messages


```
21:07:26.84 TSU00010 00000090 $HASP100 WELLIE0 ON TSOINRDR
21:07:27.09 TSU00010 00000090 $HASP373 WELLIE0 STARTED
21:07:35.21 POSIXCON 00000090 slip
    set,a=svcd,c=0c4,enable,sdata=(csa,sum,trt,psa,nuc,sqa,grsq,rgn,lpa),end
21:07:35.22 POSIXCON 00000090 IEE727I SLIP TRAP ID=0001 SET
21:09:35.53 JOB00011 00000090 $HASP100 INTIPCS ON INTRDR PETRO FROM WELLIE0
21:09:35.56 JOB00011 00000290 IRR010I USERID WELLIE0 IS ASSIGNED TO THIS JOB.
21:09:35.80 JOB00011 00000090 ICH70001I WELLIE0 LAST ACCESS AT 21:07:26 ON
    WEDNESDAY, JULY 18, 2012
21:09:35.80 JOB00011 00000090 $HASP373 INTIPCS STARTED - INIT 1 - CLASS 2
    21:09:36.82          00000090 IEA045I AN SVC DUMP HAS STARTED AT
    TIME=21.09.36 DATE=07/18/2012 523
        523 00000090 FOR ASID (0019)
        523 00000090 QUIESCE = YES
```



System Trace


- Option 2.7.4 or SYSTRACE command
 - Formats the system trace table, containing information on significant system events
 - Sample trace entries:

00-014B	008D89F0	SVC	6D	00000000_20FB1B62	0000001C	00000004	2111D5A8	Espie
				07850000 80000000				
00-014B	008D89F0	SSRV	78		8AEF2CA0	0000FA12	00000160	000060A0
						Getmain		
					014B0000			
00-014B	008D89F0	SVC	3C	00000000_20FB19EA	A0FB1720	00000100	A111D5A8	Estae
				07851000 80000000				
00-014B	008D89F0	PGM	004	00000000_20F00080	00040004	00000000		00000000
				07850000 80000000		00000000		00000000
00-014B	008D89F0*SVC		D	00000000_20FEF8B2	00000000	84000000	84000	FC7
				07851000 80000000				



VERBEXIT Command

- Calls an IBM or user-supplied verb exit
 - Optionally can provide parameters to tailor how the verb exit runs
 - Verb Exits useful for application debugging
 - LEDATA – Formats Language Environment diagnostic information as well as application information
 - OMVSDATA – Formats z/OS UNIX diagnostic information
 - DFHPDxxx – Formats CICS diagnostic information (and Language Environment info, too!)



VERBEXIT Command...

■ LEDATA Parameters

Report type parameters:

SUMMARY | ALL

HEAP | STACK | SM

HPT(value)

CM

MH

CEEDUMP

COMP(value)

PTBL(value)

Control block selection parameters:

CAA(caa-address)

DSA(dsa-address)

TCB(tcb-address)

ASID(address-space-ID)

NTHREADS(value)


Additional Component Support

■ Option 2.6 – over 50 components!

```
----- IPCS MVS DUMP COMPONENT DATA ANALYSIS -----
OPTION ===> SCROLL ===> CSR


To display information, specify "S option name" or enter S to the left
of the option desired. Enter ? to the left of an option to display
help regarding the component support.

S Name      Abstract
  ALCWAIT   Allocation wait summary
  AOMDATA   AOM analysis
  APPCDATA  APPC/MVS Data Analysis
  ASCHEDATA APPC/MVS Scheduler Data Analysis
  ASMCHECK  Auxiliary storage paging activity
  ASMDATA   ASM control block analysis
  AVMDATA   AVM control block analysis
  CICS410   CICS Version 4 Release 1 analysis
  COMCHECK  Operator communications data
  COUPLE    XCF Coupling analysis
  CSFDATA   ICSF control block analysis
  CTRACE    Component trace summary
  DAEDATA   DAE header data
  DB2DATA   DB2 analysis
  DIVDATA   Data in virtual storage
```



CBFORMAT Command


- Formats a control block
 - Syntax: CBF(ORMAT) <cbaddr> STR(<cbname>)
 - <cbaddr> can be address or symbol
 - STRUCTURE support provided by various components
 - IPCS Commands, Appendix D for MVS control blocks
 - Language Environment Debugging Guide for LE control blocks
 - CEExxx for AMODE 24/31 (CEECAA, CEECIBH, CEEDSA, CEEEDB, CEEHANC, CEESTKH, etc.)
 - CELxxxx for AMODE 64 (CELCIBH, CELDSA, CELEDB, CELLAA, CELLCA, CELSANC, etc.)



CBFORMAT Command...

- ip cbf 211201A8 str(ceedsa)
OR
ip cbf dsa1 str(ceedsa)


```
IPCS OUTPUT STREAM -----
Command ==>
*****
DSA: 211201A8
+000000 FLAGS:0000 MEMD:0000 BKC:2111D0B0      FWC:21120280
+00000C R14:A10F5776      R15:A10F7818      R0:2111D594
+000018 R1:2112023C      R2:00000000      R3:21120268
+000024 R4:A0F11000     R5:00000000      R6:21120264
+000030 R7:00000000     R8:00000001      R9:21120258
+00003C R10:2111D654    R11:A10F5558      R12:20F0FBEO
+000048 LWS:00000000    NAB:21120248      PNAB:00000000
+000064 RENT:00000000   CILC:00000000     MODE:00000000
+000078 RMR:00000000
*****
```



CBFORMAT Command...


- Can be used from Browse's Pointer Stack

```
DSNAME ('PETRO.D194.T0904332.INTIPCS') POINTERS -----
Command ===>                                                 SCROLL ===> CSR
ASID(X'014B') is the default address space
PTR   Address          Address space           Data type
00001 00.              ASID(X'014B')         AREA
Remarks:
f0002 20F0FBEO.        ASID(X'014B')         STRUCTURE (Ceecaa)
Remarks: CAA Pointer
***** END OF POINTER STACK *****
```



RUNCHAIN Command

- Allows the user to process a chain of control blocks
- User provides:
 - Starting address
 - Link offset
 - Additional parameters to tell RUNCHAIN what to do with each control block / address



RUNCHAIN Command...

```
ip runc address(211201a8) link(4) display length(x'50') name(dsa)

DSA001
LIST 211201A8. ASID(X'014B') LENGTH(X'50') AREA
ASID(X'014B') ADDRESS(211201A8.) KEY(88)
211201A8.          00000000 2111D0B0 | .....}..|
211201B0. 21120280 A10F5776 A10F7818 2111D594 |.....~....~.....Nm|
211201C0. 2112023C 00000000 21120268 A0F11000 |.....|.....1..|
211201D0. 00000000 21120264 00000000 00000001 |.....|.....|.....|
211201E0. 21120258 2111D654 A10F5558 20F0FBEO |.....O.~....0.\|_
211201F0. 00000000 21120248 |.....|
```





```
DSA002
LIST 2111D0B0. ASID(X'014B') LENGTH(X'50') AREA
ASID(X'014B') ADDRESS(2111D0B0.) KEY(88)
2111D0B0. 0808CEE1 2111D030 211201A8 A0FE3070 |.....}....y....|
2111D0C0. A0FEF7D8 2111D53C 2111D50C 20F0E7F8 |..7Q..N...N..0X8|
2111D0D0. 00000794 20FE3FA0 20F09F50 00000000 |...m....0.&....|
2111D0E0. 20F0B448 A0FE2E9A 2111F0AE 2111E0AF |.0.....0...\.|
2111D0F0. 20FDF188 20F0FBEO 00000000 211201A8 |..1h.0.\.....y|
```

RUNCHAIN Command...

```
ip runc address(211201a8) link(4) name(dsa) exec((cbf x str(ceedsa)))  
  
LIST 211201A8. ASID(X'014B') LENGTH(X'04') AREA  
ASID(X'014B') ADDRESS(211201A8.) KEY(88)  
    DSA: 211201A8  
    +000000 FLAGS:0000 MEMD:0000 BKC:2111D0B0 FWC:21120280  
    +00000C R14:A10F5776 R15:A10F7818 R0:2111D594  
    +000018 R1:2112023C R2:00000000 R3:21120268  
    +000024 R4:A0F11000 R5:00000000 R6:21120264  
    +000030 R7:00000000 R8:00000001 R9:21120258  
    +00003C R10:2111D654 R11:A10F5558 R12:20F0FBEO  
    +000048 LWS:00000000 NAB:21120248 PNAB:00000000  
    +000064 RENT:00000000 CILC:00000000 MODE:00000000  
    +000078 RMR:00000000  
  
LIST 2111D0B0. ASID(X'014B') LENGTH(X'04') AREA  
ASID(X'014B') ADDRESS(2111D0B0.) KEY(88)  
    DSA: 2111D0B0  
    +000000 FLAGS:0808 MEMD:CEE1 BKC:2111D030 FWC:211201A8  
    +00000C R14:A0FE3070 R15:A0FEF7D8 R0:2111D53C
```


Sources of Additional Information





Sources of Additional Info

- All Language Environment documentation is available on the z/OS DVD collection and on the Language Environment website
 - [Language Environment Debug Guide](#)
 - Language Environment Runtime Messages
 - Language Environment Programming Reference
 - Language Environment Programming Guide
 - Language Environment Customization
 - Language Environment Migration Guide
 - Language Environment Writing ILC Applications
- Language Environment Web site
 - http://www-03.ibm.com/systems/z/os/zos/features/lang_environment/



Sources of Additional Info...

- IPCS documentation is available on the z/OS DVD collection
 - MVS IPCS Commands
 - MVS IPCS User's Guide